

InstallReadMe - Adobe® Photoshop® 7.0
April 2002

Installing Adobe Photoshop

Before you can use Photoshop 7.0 or the ImageReady™ 7.0 component, you must install Photoshop onto your hard drive; you cannot run Photoshop from the Application CD.

To install Photoshop 7.0 in Windows:

1. Insert the Application CD into your CD-ROM drive.
2. Do one of the following:
 - If the CD launches automatically, use the buttons on-screen to start the Photoshop installer.
 - If the CD does not launch automatically, click the Start button, choose Run from the menu, click Browse, choose the CD-ROM icon from the Look In menu, double-click Setup.exe in the Adobe Photoshop 7 folder, and click OK in the Run dialog box.
3. Click Next in the Setup dialog box.
4. A warning dialog box prompts you to close all Adobe applications before proceeding to avoid restarting your system after installation. Click OK.
5. Choose the country in which you are located, and click Next.
6. Read the end user license agreement, and click Accept.
7. Enter your name and company information, and type the serial number exactly as it appears on the registration card or on the inside cover of the CD holder. Then click Next, and confirm that the information you entered is correct.
8. Specify the type of installation you want:
 - To use the standard installation, choose Typical.
 - To install only particular components, choose Custom Install, and then select the desired components. When you select a component, its description appears in the dialog box.
9. If you want to change the installation location, click Browse, and then specify a destination folder.
10. Click Next.
11. Choose whether or not to install the Adobe SVG Viewer (a plug-in that allows you to view rich dynamic graphics, text, and images in a Web browser). Click either Install or Skip. (If you chose a custom install, the SVG dialog box will not show because it is one of the custom install components.)
12. Specify file type associations, and click Next:
 - To associate Photoshop or ImageReady with a file type, select the file type in the list and select Photoshop or ImageReady. When you double-click a file of a certain type on the desktop or in Windows Explorer, the associated application is automatically launched. This association overrides any other application that may originally have been associated with the file type.
 - To continue automatically launching the original application associated with a file type, select the file type in the list and select NC (No Change). You must select NC for a file type if you want to prevent that file type from launching Photoshop or ImageReady automatically.
13. Click Next, and follow the on-screen instructions to complete the installation.
14. When the installation process is complete, a message tells you that Photoshop is installed. Click Finish.

To install Photoshop 7.0 in Mac OS:

IMPORTANT: If you choose to install Adobe Photoshop 7.0 in OS X, a warning message may appear to alert you that no Classic volume is selected. If so, quit the installer and go to System Preferences Classic. Select the volume on which your Classic environment is installed, and then quit the System Preferences and begin installation again. (If you don't have a Classic volume, the Photoshop 7.0 installer will alert you that no Classic environment is installed, and you will only be able to run Photoshop 7.0 in OS X native mode.)

1. Insert the Application CD into your CD-ROM drive.
2. Double-click the CD icon on the desktop, and double-click the Install Adobe Photoshop icon.
3. Click Continue.
4. Choose the country in which you are located from the menu at the top of the dialog box.
5. Read the end user license agreement, and click Accept.
6. If you are installing in OS X, enter an administrator's user name and password to complete the installation and click OK.
7. Enter your name and company information, and type the serial number exactly as it appears on the registration card or on the inside cover of the CD holder. Then click Next.
8. Review the registration information on the screen. If the information is correct, click Continue. If the information is not correct, click the <Back button and make corrections.
9. Review the Adobe Photoshop Read Me file. After reading the file, click Continue.
10. Specify the type of installation you want:

- To use the standard installation, choose Easy Install from the pop-up menu.
 - To install only particular components, choose Custom Install, and then select the desired components. For a description of any component that can be installed, click the "I" button to the right of the component.
11. If you want to change the installation location, choose Select Folder from the pop-up menu, and then specify a folder.
12. When the installation process is complete, a message tells you that Photoshop is installed. Click Quit.

NOTE: If you experience difficulty installing Photoshop, restart your computer with minimal system extensions and repeat the installation procedure. In particular, disable the Intellimouse control panel before repeating the installation procedure. For more information on control panels and extensions, see your Mac OS documentation.

After installing Photoshop, please register your copy using the online registration software (if you have a modem and the software is available in your version of the program), or fill out and return the enclosed warranty registration card. Registering your software allows Adobe to continue to provide you with the highest-quality software, offer technical support, and inform you about new Photoshop software developments.

Mac OS 9 to OS X Tune Up:

OS 9 and OS X have different locations for application support files (spelling dictionaries, fonts, etc.). If you've installed Photoshop 7.0 on a computer with only OS 9 and you upgrade to OS X, you need to run the OS 9 to OS X Tune Up custom install option. The Tune Up installs a full set of application support files to your OS X system folder. This will let you run Photoshop and ImageReady natively under OS X with full functionality.

The Mac OS 9 to OS X Tune Up option only appears when the installer is launched under OS X and the custom install option is selected. The Tune Up can also be used to re-install the native application support files if they have been corrupted or deleted.

Starting Adobe Photoshop

To use Photoshop or ImageReady, you must have installed the files from the CD onto your local hard drive.

To start Adobe Photoshop in Windows:

Do one of the following:

- To start the main Photoshop application, choose Start > Programs > Adobe Photoshop 7.0.
- To start the ImageReady component, choose Start > Programs > Adobe ImageReady 7.0.

To start Adobe Photoshop in Mac OS:

Do one of the following:

- To start the main Photoshop application, open the Adobe Photoshop 7 folder in the installation location you specified, and double-click the Adobe Photoshop 7.0 program icon.
- To start the ImageReady component, open the Adobe Photoshop 7 folder in the installation location you specified, and double-click the Adobe ImageReady 7.0 program icon.

=====
Adobe, the Adobe logo, ImageReady, and Photoshop are trademarks of Adobe Systems Incorporated. Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the U.S. and/or other countries. Apple, Macintosh, and Mac are trademarks of Apple Computer, Inc. registered in the U.S. and other countries. All other trademarks are the property of their respective owners.
© 2002 Adobe Systems Incorporated. All rights reserved.=====